

How to Map a Shared Library to a Network Drive


Please follow the steps below to map a shared library to a network drive.

Take the two paths as examples:

- Original Share Library path: C:/WCMDData/Library/
- New Share Library path: \\RemotePC\Share\Library


► STEP1

New Share Library: The Library should be with “Everyone” account and allow read/write privileges




▶ STEP2

Stop the web server: Click Start | Program | DT Research | Stop Web Server

**▶ STEP3**

Copy the "00000001" folder under C:/WCMDData/Library/, then paste to the new share library.
Path: \\RemotePC\Share\Library




▶ STEP4

Rename "C:/WCMDData/Library/00000001" to "C:/WCMDData/Library/00000001.bak"

▶ STEPS5


Run "cmd.exe"

mklink /D "C:\WCMDData\Library\00000001" "\\RemotePC\share\Library\00000001"



► **STEP5**

Go to Services > WebDT Content Manager WebServer > Properties > Log On, then add the account and password.



► **NOTE** If there are other site IDs, such as “00000002~ 0000000X”, please follow Steps 3 to 5 to backup and map.